

VITRIC



Kiln Synthesizer

USER MANUAL | VERSION 1.1.0 | UPDATED OCTOBER 21, 2026 | MUSE HUB EDITION

Contents

01	Quick start
02	What's new in 1.1.0
03	Earlier updates
04	The window
05	The Play page
06	The Library
07	The sill
08	The Voice page
09	The Source page
10	The Filter page
11	The Drive page
12	The Effects page
13	The Output page
14	The Motion page
15	Settings in your DAW only
16	Anneal and tuning
17	Keyboard and mouse
18	Recipes
19	Quality, CPU and old sessions
20	Specifications
21	Installation and updates
22	Troubleshooting

Kiln Synthesizer is a software instrument for basses, leads, pads, keys and plucks. It has three oscillators, two filters with a glass resonator, a per-voice drive built for 808s and sub basses, a pitch knock, a master clipper with Bass Mono, Chord Glide, four envelopes, four LFOs with fade-in, a 48-route modulation matrix, an arpeggiator and nine effects. It ships with 683 factory sounds.

This manual covers Kiln Synthesizer 1.1.0 as Muse Hub installs it: AU, VST3 and AAX on macOS, VST3 and AAX on Windows.

01 Quick start

- 1 Create an instrument (MIDI) track in your DAW and load **Kiln Synthesizer** on it. Kiln makes sound from notes; it is not an effect for an audio track.
- 2 Play your MIDI keyboard, or click Kiln's window and type: `a s d f g h j k l ;` play the white keys from C4 up, and `w e t y u o p` above them play the black keys.
- 3 Click **Library**, choose **Bass** under Type, and click a sound: it loads, and you can play it straight away while the Library stays open. `Up` and `Down` step through the list; `Esc` closes it. The arrows next to the sound's name (or `[` and `]`) also step through sounds, with the Library open or closed.
- 4 Turn the macros on the **Play** page. Each macro the sound uses is named for what it changes, such as Drive or Punch; one that reads Not assigned does nothing in this sound.
- 5 Click **Save**, type a name, pick one of the seven types and click **Save** to keep your version as one of your own sounds.

TIP

On a bass, open any page but Play. On the sill, the row of voice controls above the four macros, choose **Legato**, set **Glide** to about 70 ms and click **Exp** under its readout. Overlapping notes then slide into each other, the way an 808 does.

02

What's new in 1.1.0

A free update for every Kiln owner.

59 new factory sounds, and the best come first. 12 pads, 12 keys, 12 plucks, 13 leads, 3 808s, 5 gliding and gritty basses and 2 subs, each with four macros named for what they do. A new Kiln opens on Slow Pour, a warm sliding 808, instead of a bare saw; a plain **Init** is the first row of Factory in the Library.

A new Library. It opens over the controls and leaves the keys live: click a sound and play it at once, step through the list with Up and Down, and close it with Esc to keep what you were playing. Featured sounds first, Favourites, seven types, character words, packs, search and sort. See [The Library](#).

A Legacy shelf. 212 older factory sounds, the earlier basses and near-copies of other sounds, sit on one shelf at the end of the Library. Nothing is removed: every sound keeps its name, and songs that use them sound the same.

Chord Glide, rebuilt. Each note leaves fast, settles softly into the new chord and lands a touch apart from the others, like an analog poly. It works whether you let go of the last chord, play legato or hold the sustain pedal, and a single note added to a held chord never moves it. Switching it on while Glide is Off sets Glide to 180 ms. Projects made with Kiln 1.0 keep the Chord Glide they were made with. See [The sill](#).

Every page in the glass face. Voice, Source, Filter, Effects, Output and Motion now use the same knobs, words and glass as the Play and Drive pages. The glass shows what each page edits: the EQ's curve, the filter's response, the envelope or LFO shape, the oscillator's wave or sample.

About forty settings that lived only in your DAW now have a control, such as the filter routing and slope, Filter Balance in Split, Saturation Mix, Delay's low and high cut, the Sub's wave and octave, the noise filter, voices, MPE, bend range, envelope loop, LFO sync rate, and each oscillator's unison stack, warp, FM, ring and sync. Filter FM, on each filter, is the one working setting left only in your DAW; see [Settings in your DAW only](#).

Sound fixes. Six wavetables (PWM Sweep, Sync Sweep, Bend Low, Bend High, S-Fold and Knee) lose a DC offset that thumped at the start and end of notes. A Glass filter's Mix and a wavetable's Warp Amount now follow the modulation matrix, and the Sync warp sweeps smoothly. A few factory sounds are fixed: on Glass Ladder, Super Glide, Chip Hop and Tin Comet, Bright now adds bite; Burnt Glow and Burnt Lantern lose their high fizz; Buzz Cinder and Long Cinder end their notes cleanly. The Utility's DC block and LFO Smooth behave the same at 96 and 192 kHz as at 48 kHz. Projects made with Kiln 1.0 sound as they did.

Your sounds where every host can see them. In Logic, GarageBand and MainStage, your sounds now save in the same folder as in every other host. Sounds saved in those hosts before 1.1 still show up.

The waveform on Windows. The glass now draws the waveform line of the sound you play on Windows too, as it does on macOS.

Smaller fixes. Compressor Attack and Release and Reverb Pre-delay read in ms in your DAW's automation lanes; the Voices control covers its full 1 to 64; the LFO display draws the shape you hear.

The Field timbre map is retired. The Library's types, words and favourites replace it. Anneal stays in the options menu.

Your songs are safe. No parameter was added, removed or renamed. A project or a user sound saved with an earlier Kiln opens with the engine it was made with, and sounds exactly as it did.

03 Earlier updates

1.0.2: no click when you let go of a note on sounds with a curved release; sounds and A/B recall exactly; a little lighter on Windows.

1.0.1: Knock, the Clipper and Bass Mono got their own views on the Drive page; the glide curve (Lin or Exp) on the sill; LFO fade-in on the face; readouts in plain units; the modulation matrix in words.

1.0: the glass face and the Play page; Chord Glide; a bass engine (per-voice drive with six characters and Low Keep, Knock, an exponential glide, Clean Legato, Bass Mono and a master clipper); LFOs that fade in; 70 new factory sounds (64 basses and 6 leads); cleaner drive and soft clip. Obsidian 1.1 came with it, a free update for Obsidian owners.

04 The window

Kiln's window has four parts that stay in place: the header at the top, the page names under it, the key bed at the bottom, and the page itself in the middle. On every page except Play, the lower right holds the sill (the voice controls) above the preset's four macros, so the controls you reach for most are always in sight. Most pages show one part at a time: the words at a page's top right pick its views, and the glass on the left draws what the page edits.



FIG. 1

The Source page, Osc 1 on a wavetable: the oscillators and the views across the top, the glass drawing the wave, the sill and the four macros at the lower right.

- | | |
|--|---|
| <p>1 Oscillators. Osc 1, Osc 2 and Osc 3; the bright one is shown.</p> <p>3 The glass. What the page edits; here, the oscillator's wave.</p> <p>5 The sill. Voice mode, Chord Glide, Clean Legato, Glide and its curve.</p> | <p>2 Views. Sound, Unison and Pitch. Click a word to switch.</p> <p>4 Controls. The shown oscillator's controls for this view.</p> <p>6 Macros. The preset's four macros, on every page.</p> |
|--|---|

The header and pages




FIG. 2 The header, and the eight page names under it.

- 1

Previous and next. Step through sounds. [] and [] do the same.
- 2

Sound name. The sound's name, with its type and where it comes from, such as 808 · Factory. Click to open the Library.
- 3

Save. Opens the Library on its save row.
- 4

Library. Browse, play, search and save sounds.
- 5

License. Reads Muse Hub. This edition opens unlocked, so the word is a label and takes no clicks.
- 6

Options (⋮). Tooltips, keyboard shortcuts, update checks, tuning and Anneal.
- 7

Pages. Play, Voice, Source, Filter, Drive, Effects, Output and Motion. Keys 1 to 8 open them in order.

The key bed



FIG. 3 The key bed: computer-key range, the on-screen keys, and the output.

- 1

Computer keys. The range your computer keyboard plays. The arrows (or [z] and [x]) move it an octave.
- 2

Keys. Click to play. Notes from your DAW or MIDI keyboard light the keys too.
- 3

Typing range. The bracket under the keys marks what the computer keys reach.
- 4

Low Keep mark. On the Play and Drive pages, while Drive is on, the drive's Low Keep frequency shows at its note.
- 5

Out. Kiln's master output.
- 6

Meter. The output level.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
COMPUTER KEYS	Moves the computer-keyboard range by octaves.		C4 to E5
KEYS	Click a key to play it. Notes from your DAW or MIDI keyboard light their keys.	Five octaves from C2	
OUT	Kiln's master output level. The wheel steps 0.5 dB; double-click for 0 dB.	-60 to +12 dB	0.0 dB

05

The Play page

The Play page is for playing, not editing: the glass window shows what you hear, and the macros are the moves the sound designer chose for this sound.




FIG. 4

The Play page on Tight Fuzz: the four macros a new 1.0 bass carries, and the glass window on a held E4.

- 1

Macro 1. Named by the preset (here, Drive).
- 2

Macro 2. Here, Blend.
- 3

Macro 3. Here, Punch.
- 4

Macro 4. Here, Tone.
- 5

Note or chord. One or two held notes show their names; three or more show the chord.
- 6

Waveform. The sound as it plays, steady on the lowest note.
- 7

Spectrum. The sound's frequency content, low on the left.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
MACROS 1 TO 4	Each moves everything the sound routes to it. The name comes from the preset (a macro the sound doesn't name shows the first control it moves); a macro the sound does not use reads Not assigned and is dimmed. Click the value to type one.	0 to 100 %	Set by the preset

The new basses and leads

On the 64 basses new in 1.0 the macros are **Drive**, **Blend** (or **Sub** on eight of them), **Punch** and **Tone**:

Drive raises the drive amount.

Blend brings the clean voice back in under the drive (it lowers the drive's Mix). Where that slot is **Sub**, it sets the sub oscillator's level.

Punch shortens the amp envelope and adds Knock at the same time.

Tone moves the filter or the oscillator shape.

On the six new leads they are **Bright**, **Vibrato**, **Shape** and **Pluck**. **Bright** adds bite on four of them (it brings in the drive) and moves the filter on the other two (its cutoff or its resonance); **Shape** moves the oscillator's shape. **Vibrato** sets the vibrato depth and **Pluck** shortens the amp envelope.

The 59 sounds new in 1.1 name their macros the same way, for what each one does in that sound.

NOTE

Of the 70 new sounds, 33 use Knock, 43 use Bass Mono, 30 use the Clipper, 40 use the Exp glide curve, all 70 use Clean Legato, and the 6 leads use the LFO fade-in. You find them in the Drive page's **Knock** and **Clipper** views, on the sill, and in the Motion page's **LFOs** view.

06

The Library

Click **Library** in the header (or the sound's name). The Library opens over the controls and leaves the keys live: click a sound and play it straight away, on the on-screen keys, your computer keys or MIDI.



FIG. 5

The Library on Featured, with Obsidian installed and Slow Pour loaded: the shelves on the left, the list in the middle, and the sound's glass and macros on the right.

- 1 **Featured, Favourites, All sounds.** Each time you open Kiln's window, the Library first opens on Featured: 36 of the best factory sounds, mostly leads, basses and 808s with a few pads, keys and plucks, starting with Slow Pour, the sound a new Kiln opens on. If you own Obsidian, 16 of its sounds are featured too. When the sound you are on is not featured, that first open goes to All sounds instead. Favourites are the sounds you starred. While the window stays open, the Library reopens where you left it, or on All sounds if the sound you are on is not in that view. The types, packs, words and search below work inside the one you choose here, so choose **All sounds** to look through everything.
- 2 **Type.** Bass, 808, Lead, Pad, Keys, Pluck and FX. The number beside each is how many sounds it would show. Click a chosen type again to clear it.

- 3 **Packs.** Factory (471 sounds plus **Init** at the top: one saw, everything else off, to start from scratch), each expansion pack you own, Your sounds and, last, Legacy (212 older factory sounds, kept so your songs still find them). In All sounds, pick a type with a pack to see, say, the legacy pads. Click a chosen pack again to clear it.
- 5 **Sort.** Best (our order within each type), A–Z, or Pack.
- 7 **Star.** Adds the sound to your Favourites, or takes it out.
- 9 **Macros.** The sound's four macros, live: turn them while it plays.
- 11 **Save.** Name your sound, pick its type and click **Save**.
- 4 **Search.** Narrows the list: it reads names, types, packs, character words and descriptions, so in All sounds "legacy bass" finds the older basses.
- 6 **Character words.** Dark, Bright, Warm, Driven, Glide and the rest. Pick one or more; a sound must have them all.
- 8 **The glass.** Shows the sound as you play it.
- 10 **Play a phrase.** Plays a short line that suits the sound's type; it reads Stop while it plays.

Click a row to load it. **Up** and **Down** (and **Page Up**, **Page Down**, **Home** and **End**) step through the list and load as they go; **Enter** loads the selected row. A double-click loads and closes. **Esc**, **Library** again or any page name closes the Library, and the sound you were playing stays.

Typing in Search or the name box sends the keys to the box; click the list again to play.

Factory sounds never change: **Save** always makes your own copy, and the Library tells you if the name is taken or the file could not be written.

[and **]** (or the header arrows) step through the factory sounds, then your packs, then your own sounds, with the Library open or closed.

Your favourites are kept in one file beside your own sounds, so every project sees the same stars.

Expansion packs

A Vitric Sounds expansion pack, such as Obsidian, downloads as a zip. Unzip it and put its **.xml** pack files straight into Kiln's Expansions folder (not in a folder inside it), which Kiln creates the first time you open the Library, then open the Library again. Until a pack is installed, the Library shows the folder under Packs.

macOS: `~/Library/Vitric Audio/Kiln/Expansions`

Windows: `%APPDATA%\Vitric Audio\Kiln\Expansions`

The pack appears under Packs, and its sounds join All sounds and the types. Put every file from the zip in the folder: each Kiln plays the newest version it can read. Obsidian 2.1 (93 sounds) needs Kiln 1.1; Obsidian 2.0 (91 sounds) and 1.1 (66 sounds) work from Kiln 1.0; Kiln 0.3 keeps using Obsidian 1.0. When a newer version of a pack you own is out, the Library says so under Packs. A session saved with a pack sound reopens with its sound and name even if you later remove the pack.

07

The sill

These voice controls sit at the lower right of every page except Play, above the four macros.



FIG. 6 The sill on Tight Fuzz: voice mode, Chord Glide, Clean Legato, Glide and its curve, above the four macros.

- 1

Voice mode. Poly, Mono or Legato.
- 2

Chord Glide. Each note of a new chord slides from the nearest note of the last chord. Its state reads under it.
- 3

Clean Legato. Slides and re-attacks without clicks.
- 4

Glide. How long a slide takes.
- 5

Glide curve. Lin or Exp.
- 6

Macros. The same four macros as on the Play page.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
POLY · MONO · LEGATO	Poly plays chords. Mono plays one note at a time, re-attacks every note and slides only between notes that overlap (turn Legato only off on the Voice page to make it slide into every note). Legato plays one note at a time and slides between overlapping notes without re-attacking.	Poly, Mono, Legato	Poly
CHORD GLIDE	In Poly, each note of a new chord slides from the nearest note of the last chord (let go, still held, or held by the sustain pedal), over the Glide time. With Glide at Off, chords do not slide, so turning Chord Glide on while Glide is Off also sets Glide to 180 ms, in one undo step; a Glide you have set is left alone. The line under it reads On · Poly, Needs Poly (on, but in Mono or Legato) or Off · Poly only.	On or off	Off

CONTROL	WHAT IT DOES	RANGE	DEFAULT
CLEAN · LEGATO	A sounding voice keeps its phase and filter state through a slide or a re-attack, so slides never click. On in every new 1.0 sound. Reads On · no clicks or Off.	On or off	Off
GLIDE	How long a slide takes; Chord Glide uses the same time. A bare number is read as seconds up to 5 and as milliseconds above 5, so 70 gives 70 ms.	Off to 5 s	Off
LIN · EXP	The glide curve. Lin: the pitch moves at an even speed. Exp: it leaves fast, then settles into the note, like an 808 slide.	Lin, Exp	Lin

Chord Glide, step by step

- 1 Set the voice mode to **Poly**.
- 2 Turn on **Chord Glide**. The line under it reads On · Poly, and if Glide was Off it is now 180 ms, a good place to start.
- 3 Play a chord, then the next one. Each note of the new chord slides from the closest note of the last one and lands softly, so the voices move like a section of players. Voices never cross, and a three-note chord can move to a four-note chord.

The last chord can be one you just let go of (within about a second and a half), one you are still holding when two or more new notes land together (the held notes move into the new chord without a new attack), or one the sustain pedal holds. A single note added to a held chord never moves it. A quick roll (all notes within about 30 ms) glides as one chord. Projects saved with Kiln 1.0 keep the Chord Glide they were made with.

08

The Voice page

The Voice page has two views, picked by the words **Arp** and **Voice** at its top right: the arpeggiator, and how notes become voices. The glass shows the sound you play.



FIG. 7 The Voice page, Arp view, with the arpeggiator on.

- 1

Views. Arp and Voice.
- 2

Arpeggiator. Turns the arpeggiator on.
- 3

Latch. Keeps the pattern going after you let go.
- 4

Rate. The step length, in time with your DAW.
- 5

Pattern. The order the notes play in.
- 6

Octaves. How many octaves the pattern climbs.
- 7

Gate. How long each step sounds.
- 8

Swing. Pushes every other step late.
- 9

Chance. The chance each step plays.

Arp

CONTROL	WHAT IT DOES	RANGE	DEFAULT
ARPEGGIATOR	Plays the notes you hold as a pattern at the Rate.	On or off	Off
LATCH	The pattern keeps playing after you let go; the next chord you play replaces it.	On or off	Off
RATE	The step length, a note value in time with your DAW.	8/1 to 1/64, with dotted (D) and triplet (T) values	1/16

CONTROL	WHAT IT DOES	RANGE	DEFAULT
PATTERN	The order the notes play in: Up, Down, Up-Down, As Played, Random, or Chord (the whole chord on each step). Click a word or turn the dial; the line under the dial says what it does.	6 patterns	Up
OCTAVES	How many octaves the pattern climbs.	1 to 4	1
GATE	How long each step holds, as a share of the step. Short is staccato.	5 to 100 %	60 %
SWING	Delays every other step for a shuffle.	0 to 75 %	0 %
CHANCE	The chance each step plays. The choices are seeded, so a bounce plays the same pattern every time.	0 to 100 %	100 %

Voice

CONTROL	WHAT IT DOES	RANGE	DEFAULT
VOICES	How many notes can sound at once in Poly.	1 to 64	16
TIME · RATE (GLIDE MEASURES)	Time: every slide takes the Glide time. Rate: the Glide time is per octave, so wider slides take longer.	Time, Rate	Time
LEGATO ONLY	On: Mono and Legato glide only between notes that overlap. Off: every new note glides from the last one, in every voice mode, even across a gap.	On or off	On
MPE	Auto: on when your DAW sends MPE. On or Off: always.	Auto, On, Off	Auto
BEND RANGE	How far the pitch wheel bends, up and down.	0 to 48 st	2 st
TUNE	Tunes all of Kiln.	-100 to +100 ct	0 ct
DRIFT	A slow analog wander in pitch. Seeded, so offline bounces repeat exactly.	0 to 100 %	10 %
DRIFT SPREAD	How differently each voice drifts.	0 to 100 %	15 %

09 The Source page

The Source page holds the three oscillators. Pick one with the words **Osc 1**, **Osc 2** and **Osc 3**, and one of its three views with **Sound**, **Unison** and **Pitch** at the top right; The window shows the page. The glass draws the oscillator's wave: one cycle of the wavetable frame or the analog shape, or the whole sample with its start and loop marked.

Sound

CONTROL	WHAT IT DOES	RANGE	DEFAULT
OSC 1, OSC 2, OSC 3 (SWITCH)	Turns the oscillator on.	On or off	Osc 1 on, Osc 2 and 3 off
WAVETABLE · ANALOG · SAMPLE	The engine. Wavetable scans one of 80 tables; Analog is one lane from sine to pulse; Sample plays a file you load.	3 engines	Wavetable
TABLE (< NAME >)	Wavetable: the table this oscillator plays. The arrows step through the 80 tables; click the name for the list.	80 tables	Init Saw
POSITION	Wavetable: scans through the table's frames.	0 to 100 %	0 %
WARP	Wavetable: bends the frames: Bend, Sync, PWM, Formant, Mirror, Quantize, or FM Sibling (FM from the next oscillator; Osc 3, or a next oscillator that is off, uses its own sine). Off leaves them as they are.	Off and 7 modes	Off
WARP AMOUNT	Wavetable: how far the warp goes. It does nothing while Warp is Off.	0 to 100 %	0 %
SHAPE	Analog: one lane from sine through triangle and saw to pulse. Double-click for the sine.	0 to 100 %	0 %
PULSE WIDTH	Analog: the pulse's duty, in the pulse end of the lane.	1 to 99 %	50 %
SYNC	Analog: hard-sync pitch above the note, the classic sync sweep.	0 to 48 st	0 st
START	Sample: where the sample begins, as a share of its length (from the end when reversed).	0 to 100 %	0 %
LOOP	Sample: Off plays once; Loop repeats the loop; X-fade blends across the loop's seam.	Off, Loop, X-fade	Off

CONTROL	WHAT IT DOES	RANGE	DEFAULT
REVERSE	Sample: plays the sample backwards.	On or off	Off
CROSSFADE	Sample: how much of the loop blends across its seam (X-fade only).	0 to 100 %	10 %
LEVEL	The oscillator's level.	0 to 100 %	75 %
PAN	Its place, left to right. Double-click for the centre.	Left 100 % to Right 100 %	Centre

Loading a sample

Pick **Sample**, then click **Load** to choose a WAV, AIFF or FLAC file, or drop a file on the Source page's controls, on the right: it loads into the shown oscillator and switches it to Sample. **Clear** removes it. The sample's name shows beside Load. Kiln reads the root key from the file's sampler data when it has any, otherwise from a pitch analysis (C4 when the sound has no clear pitch). The session keeps a copy of each sample, up to 16 MB per sound; beyond that it saves a link to the file. If the linked file has moved, the name reads Missing: and the file's name; click **Load** and choose it again. Long files load their first 2,097,152 samples (about 48 s at 44.1 kHz).

Unison

CONTROL	WHAT IT DOES	RANGE	DEFAULT
VOICES	How many stacked copies each note plays. More copies cost more CPU.	1 to 16	1
UNISON · OCTAVE · FIFTH (STACK)	Unison: every copy at the note. Octave or Fifth: copies stacked an octave or a fifth apart.	3 stacks	Unison
STEREO · PHASE · TABLE · FORMANT (SPREAD ACROSS)	What the copies differ in: stereo place, start phase, table position or formant.	4 kinds	Stereo
DETUNE	How far the outer copies are detuned.	0 to 100 ct	12 ct
SPREAD	How far the copies spread.	0 to 100 %	60 %
BLEND	How loud the outer copies are against the centre.	0 to 100 %	70 %
DETUNE CURVE	How the detune spreads across the copies.	Linear, Exponential, Custom	Linear

Pitch

CONTROL	WHAT IT DOES	RANGE	DEFAULT
OCTAVE	Coarse pitch.	-4 to +4	0
SEMITONE	Pitch in semitones.	-12 to +12 st	0 st
FINE	Fine pitch.	-100 to +100 ct	0 ct
PHASE	Where the wave starts, with Retrigger.	0 to 360°	0°
RETRIGGER	Free: the wave runs on. Retrig: every note starts at Phase. Random: every note starts somewhere new.	Free, Retrig, Random	Free
FM FROM	Which oscillator modulates this one's phase. Only a higher-numbered oscillator that is on works (Osc 1 from Osc 2 or 3). Wavetable and Analog only.	None, Osc 1, Osc 2, Osc 3	None
FM AMOUNT	How hard the FM source pushes. Wavetable and Analog only.	0 to 100 %	0 %
ROUTE	Where this oscillator goes: Filter 1, Filter 2, both, or straight past the filters.	Filter 1, Filter 2, Both, Direct	Filter 1
RING	Multiplies this oscillator by the one chosen in FM from, which must be higher-numbered, so Ring never works on Osc 3. It does nothing while FM from is None or a lower oscillator. If that oscillator is off or at Level 0, this one goes silent.	On or off	Off
SYNC	Hard-syncs this oscillator to the next one's pitch: Osc 1 to Osc 2, Osc 2 to Osc 3, Osc 3 to Osc 1. Wavetable and Analog only.	On or off	Off

10

The Filter page

Two filters. Pick one with **Filter 1** or **Filter 2**; **Serial**, **Parallel** and **Split** at the top right set how they connect. The glass draws the shown filter's real response (the other filter faint behind it, when it is on) with a point for cutoff and resonance: drag it, or double-click it to reset both. The Glass model draws its modes instead, without the point.



FIG. 8

The Filter page on Pulse Furnace in Split routing, Balance at Filter 1 40 %, an SVF at 600 Hz.

- 1

Filters. Filter 1 and Filter 2.
- 2

Routing. Serial, Parallel or Split.
- 3

Balance. In Split, how far each filter reaches into the other side.
- 4

Cutoff. Where the filter acts.
- 5

Model. SVF, Ladder, Comb, Formant or Glass.
- 6

Resonance. Emphasis at the cutoff.
- 7

Drive. Heat into the Ladder.
- 8

Keytrack. How far the cutoff follows the note.
- 9

Morph. Low to band to high pass, or the vowel.
- 10

Mix. Unfiltered and filtered blend.
- 11

Slope. 12 or 24 dB an octave.
- 12

The point. Cutoff and resonance in the glass.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
SERIAL · PARALLEL · SPLIT (ROUTING)	Serial: Filter 1 feeds Filter 2. Parallel: each filters what its oscillators send it. Split: Filter 1 left, Filter 2 right.	3 routings	Serial

CONTROL	WHAT IT DOES	RANGE	DEFAULT
FILTER 1, FILTER 2 (SWITCH)	Turns the filter on.	On or off	Filter 1 on, Filter 2 off
CUTOFF	Where the filter acts. Drag the knob or the point in the glass; Shift is fine.	20 Hz to 20 kHz	20.0 kHz
MODEL	SVF (low, band or high pass by Morph), Ladder, Comb, Formant, or Glass, the resonator Kiln is named for. Click a word or turn the dial; the line under it says what it does.	5 models	SVF
RESONANCE	Emphasis at the cutoff. The Ladder sings near the top.	0 to 100 %	15 %
DRIVE	Ladder only: heat into the ladder.	0 to 24 dB	0.0 dB
MORPH	SVF: low pass through band pass to high pass. Formant: sweeps the vowel.	0 to 100 %	0 %
MIX	Blend of the unfiltered sound and the filtered one.	0 to 100 %	100 %
KEYTRACK	How far the cutoff follows the note you play.	0 to 100 %	0 %
12 DB · 24 DB (SLOPE)	SVF only: how steep it cuts, per octave.	12 dB, 24 dB	24 dB
BALANCE	Split only. Filter 1 plays on the left, Filter 2 on the right; turn left and Filter 1 also fills the right side, turn right and Filter 2 fills the left. Centre: each reaches halfway. Double-click for the centre.	Filter 1 100 % to Filter 2 100 %	Centre

The Glass resonator

With **Glass** chosen, the filter shows its own controls, with Material as the large knob. The resonator rings at each note you play, so you play it like an instrument: start from a sound with the **Glass** character word, move Material and Position, then set Damping for the length of the ring.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
MATERIAL	What the resonator is made of: glass, metal in the middle, then wood.	0 to 100 %	20 %
SIZE	The body: small rings high, large rings low.	0 to 100 %	50 %
POSITION	Where it is struck; it picks which modes ring.	0 to 100 %	30 %
DAMPING	How fast the ring dies; the high modes go first.	0 to 100 %	40 %
SHIMMER	A slow drift in the modes that keeps the ring alive.	0 to 100 %	15 %

CONTROL	WHAT IT DOES	RANGE	DEFAULT
MODES	How many partials ring. More is richer and costs more CPU.	4 to 64	24
FOLLOWS NOTE	On: tuned to each note you play. Off: it rings at one fixed pitch.	On or off	On
MIX	As above.	0 to 100 %	100 %

11 The Drive page

The Drive page has three views, picked by the words **Drive**, **Knock** and **Clipper** at its top right. Drive and Knock work on each voice; the Clipper and Bass Mono work on Kiln's master output. The glass window on the left shows the sound in every view. Each time you open Kiln's window, the page starts on the Drive view.

The Drive view

The drive works on each voice separately, after the filter, so every note of a chord distorts on its own and a bass keeps its shape under heavy drive.



FIG. 9

The Drive view on Tight Fuzz: Fuzz at 18.0 dB, Bias 40 %, Low Keep at 80 Hz.

- | | |
|--|--|
| <p>1 Drive. Turns the drive on.</p> <p>3 Type. The drive's character.</p> <p>5 Low Keep. Keeps the lows below it clean.</p> <p>7 Mix. Clean and driven blend.</p> <p>9 Views. Drive, Knock and Clipper. Click a word to switch.</p> | <p>2 Drive (the large knob). How hard each voice is driven.</p> <p>4 Bias. Adds even harmonics to some types.</p> <p>6 Tone. Darker or brighter.</p> <p>8 Output. Level after the drive.</p> |
|--|--|

CONTROL	WHAT IT DOES	RANGE	DEFAULT
DRIVE	Turns the per-voice drive on or off. The Drive view's controls dim while it is off.	On or off	Off
DRIVE (THE LARGE KNOB)	How hard each voice is driven.	0 to 36 dB	12.0 dB
TYPE	The drive's character: Soft, Tube, Hard, Fold, Fuzz or Even (listed below). Click a word or turn the dial.	6 types	Soft
BIAS	Adds asymmetry (even harmonics) to Tube, Fuzz and Even. No effect on Soft, Hard or Fold; the note under it says so.	0 to 100 %	0 %
LOW KEEP	Everything below this frequency stays clean under any drive, so the sub holds. Off at full left. The frequency also shows as a mark on the keys while Drive is on.	Off, 20 to 300 Hz	Off
TONE	Darker to the left, brighter to the right, Flat in the centre. Double-click for Flat.	Dark 100 % to Bright 100 %	Flat
MIX	Blend of the clean voice and the driven one.	0 to 100 %	100 %
OUTPUT	Level after the drive. The wheel steps 0.5 dB; double-click for 0 dB.	-24 to +12 dB	0.0 dB
HEAT METER	The drive's input and output levels, and how much heat it adds. With Drive on and nothing playing, it shows, dimmed, what the drive adds at -6 dB in. With Drive off it reads Off.		

The six types:

Soft: smooth, round saturation.

Tube: warm, asymmetric glow.

Hard: tight, bright hard clip.

Fold: folds the wave over itself.

Fuzz: pulse fuzz; Bias sets the growl.

Even: even-harmonic growl.

Knock

Knock is a pitch sweep into every note: each note starts away from its pitch and sweeps in, the punch of an 808. It moves every oscillator and the sub.



FIG. 10 The Knock view on Tight Fuzz: Knock at +9 st, landing in 30 ms.

- 1

Views. Drive, Knock and Clipper.
- 2

Knock. How far the pitch starts from the note.
- 3

Decay. How long the sweep takes.
- 4

Curve. The shape of the sweep.
- 5

On slides. Whether legato slides get the sweep.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
KNOCK	How far each note's pitch starts from the note. Above the note it falls in like an 808's knock; below, it rises. Double-click for Off.	-48 to +48 st	Off
DECAY	How long the sweep takes to land on the note. A bare number is read as seconds up to 1 and as milliseconds above 1, so 30 gives 30 ms.	1 ms to 1 s	40 ms
CURVE	The sweep's shape: 0 % falls in a straight line; higher values drop fast first, then settle.	0 to 100 %	60 %
ON SLIDES	Off: only notes that start fresh get the sweep, and the line under it reads Fresh notes only. On: legato slides get it too (Slides too).	On or off	Off

The Clipper and Bass Mono

The Clipper sits on the master, after the effects and after Bass Mono. It holds peaks just under 0 dB.



FIG. 11 The Clipper view on Tight Fuzz: the Clipper on with Drive at 4.0 dB, Bass Mono at 120 Hz.

- 1

Clipper. Turns the master clipper on.
- 2

Drive. How hard the master is pushed into it.
- 3

Knee. How softly it rounds the peaks.
- 4

Bass Mono. Lows in mono below this frequency.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
CLIPPER	Turns the master clipper on or off. Drive and Knee are dimmed while it is off.	On or off	Off
DRIVE	How hard the master is pushed into the clipper.	0 to 24 dB	0.0 dB
KNEE	How softly the clipper rounds the peaks: 0 % is a hard corner, 100 % the softest.	0 to 100 %	30 %
BASS MONO	Everything below this frequency plays in mono on the master, so the low end stays centred. Off at full left. It works with the Clipper on or off.	Off, 20 to 300 Hz	Off
NOTE	The Clipper is not Soft clip on the Output page. Soft clip is a gentle ceiling, on by default, that comes after the Clipper. Out comes last, so with Out above 0 dB the peaks can pass 0 dB again.		

12

The Effects page

Nine effects in a chain: **EQ**, **Compressor**, **Saturation**, **Chorus**, **Phaser**, **Flanger**, **Delay**, **Reverb** and **Utility**. Click a name to show that effect; a name is bright when the effect is on and dim when it is off. Each effect's own name, at the upper left of its controls, is its on switch. Each stays off until the sound or you turn it on.



FIG. 12 The Effects page on the EQ, with its curve and three points in the glass.

- 1

Effects. The nine names; bright when on.
- 2

EQ. The EQ's on switch.
- 3

Points. Low, Mid and High in the glass.
- 4

Low. The low shelf.
- 5

Mid freq, Mid gain. The mid bell.
- 6

High. The high shelf.
- 7

Tilt. Darker or brighter overall.

EQ, compressor and saturation

CONTROL	WHAT IT DOES	RANGE	DEFAULT
EQ: THE GLASS	The EQ's curve over the sound, with three points: Low, Mid and High. Drag a point; Shift for fine; double-click to reset its gain. The knobs below move with it.		
EQ: LOW	The low shelf at 120 Hz.	-15 to +15 dB	0.0 dB
EQ: MID FREQ	Where the mid bell sits.	100 Hz to 8 kHz	900 Hz

CONTROL	WHAT IT DOES	RANGE	DEFAULT
EQ: MID GAIN	The mid bell's boost or cut.	-15 to +15 dB	0.0 dB
EQ: HIGH	The high shelf at 6 kHz.	-15 to +15 dB	0.0 dB
EQ: TILT	Leans the whole sound darker or brighter, by up to 3 dB at each end. Flat in the centre.	Dark 100 % to Bright 100 %	Flat
COMPRESSOR: CLEAN · OTT	Clean: one compressor on the whole sound. OTT: three bands, each squeezed from above and lifted from below.	Clean, OTT	Clean
COMPRESSOR: THRESHOLD	Where compression starts. Lower squeezes more.	-60 to 0 dB	-18.0 dB
COMPRESSOR: RATIO	Clean only: how hard it squeezes above the threshold.	1.0:1 to 20.0:1	3.0:1
COMPRESSOR: ATTACK	How fast it grabs. Slower lets the front of each note through.	0.1 to 200 ms	12 ms
COMPRESSOR: RELEASE	How fast it lets go.	5 ms to 2 s	140 ms
COMPRESSOR: UPWARD, DOWNWARD	OTT only: lifts the quiet parts of each band, and squeezes the loud parts.	0 to 100 %	50 %
COMPRESSOR: MIX	Blend of the dry sound and the compressed one.	0 to 100 %	100 %
SATURATION: DRIVE	How hard the sound is pushed into the saturator.	0 to 36 dB	6.0 dB
SATURATION: TYPE	Tape, Tube, Fold or Crush. Click a word or turn the dial.	4 types	Tape
SATURATION: TONE	Darker or brighter, after the saturator. Flat in the centre.	Dark 100 % to Bright 100 %	Flat
SATURATION: MIX	Blend of the clean sound and the saturated one. In projects and user sounds saved with Kiln 0.3 or earlier it shows dimmed with a note, because their saturation was always fully wet.	0 to 100 %	100 %

Chorus, phaser and flanger

CONTROL	WHAT IT DOES	RANGE	DEFAULT
CHORUS: RATE, DEPTH	How fast and how far the copies drift.	0.01 to 8 Hz; 0 to 100 %	0.40 Hz; 50 %
CHORUS: VOICES	How many copies.	2 to 4	3
CHORUS: MIX	Blend.	0 to 100 %	50 %

CONTROL	WHAT IT DOES	RANGE	DEFAULT
PHASER: RATE, DEPTH	How fast and how wide the sweep.	0.01 to 8 Hz; 0 to 100 %	0.30 Hz; 70 %
PHASER: STAGES	More stages, more notches.	2 to 8	6
PHASER: FEEDBACK	Sharpens the notches into a resonant whistle.	0 to 90 %	30 %
PHASER: MIX	Blend.	0 to 100 %	50 %
FLANGER: RATE, DEPTH	How fast and how wide the sweep.	0.01 to 8 Hz; 0 to 100 %	0.25 Hz; 60 %
FLANGER: FEEDBACK	More feedback, more metal.	0 to 90 %	50 %
FLANGER: MIX	Blend.	0 to 100 %	50 %

Delay, reverb and utility

CONTROL	WHAT IT DOES	RANGE	DEFAULT
DELAY: SYNC	On: Left and Right are note values in time with your DAW. Off: they are milliseconds.	On or off	On
DELAY: LEFT, RIGHT	The two echoes' times: note values with Sync on, milliseconds with it off.	8/1 to 1/64; 1 ms to 2 s	1/8 and 1/4; 350 ms and 500 ms
DELAY: FEEDBACK	How many repeats.	0 to 98 %	45 %
DELAY: PING-PONG	Bounces the repeats between left and right.	0 to 100 %	0 %
DELAY: WOW	A tape-style wander in the repeats' pitch.	0 to 100 %	15 %
DELAY: DIFFUSE	Smears each repeat; they stay on the grid.	0 to 100 %	0 %
DELAY: LOW CUT, HIGH CUT	Thins the repeats below, and darkens them above, these frequencies.	20 Hz to 2 kHz; 500 Hz to 20 kHz	120 Hz; 9.00 kHz
DELAY: MIX	Blend.	0 to 100 %	25 %
REVERB: SIZE	How big the space is.	0 to 100 %	50 %
REVERB: DECAY	How long the tail lasts.	0.1 to 20 s	2.20 s
REVERB: PRE-DELAY	A gap before the tail starts.	0 to 200 ms	12 ms
REVERB: DAMPING	How fast the highs die away in the tail.	0 to 100 %	40 %
REVERB: SHIMMER	Feeds a pitched copy back into the tail.	0 to 100 %	0 %

CONTROL	WHAT IT DOES	RANGE	DEFAULT
REVERB: OCTAVE · FIFTH · DETUNE	What the shimmer adds: an octave up, a fifth up, or a slight detune.	3 intervals	Octave
REVERB: WIDTH	How wide the tail spreads.	0 to 150 %	100 %
REVERB: MIX	Blend.	0 to 100 %	25 %
UTILITY: WIDTH	Stereo width: 0 % is mono, 100 % as it is, 200 % wider.	0 to 200 %	100 %
UTILITY: PAN	Left to right. Double-click for the centre.	Left 100 % to Right 100 %	Centre
UTILITY: GAIN	Level at the end of the chain.	-24 to +24 dB	0.0 dB
UTILITY: DC BLOCK	Removes any DC offset while the Utility is on. The line under it reads On or Off.	On or off	On

13

The Output page

Three views, picked by **Output**, **Sub** and **Noise** at the top right: the end of the chain, the sub oscillator, and the noise source. Drift is on the Voice page, and the macros are in the macro row.




FIG. 13

The Output page, Output view: Out, Quality, Soft clip and the Auto governor.

1

Views. Output, Sub and Noise.

2

Out. Kiln's master output.

3

Quality. Eco, Standard or Ultra.

4

Soft clip. A gentle ceiling on the master.

5

Auto governor. Keeps playback running under load.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
OUT	Kiln's master output (the same as Out on the key bed). The wheel steps 0.5 dB; double-click for 0 dB.	-60 to +12 dB	0.0 dB
QUALITY	Eco, Standard or Ultra. Eco halves unison and lightens the oscillators to save CPU; Ultra is the cleanest. Bounces always render at Ultra.	3 levels	Standard
SOFT CLIP	A gentle ceiling on the master, after the effects and the Clipper, so peaks round off instead of going over. Out comes after it. The line under it says what it is doing.	On or off	On

CONTROL	WHAT IT DOES	RANGE	DEFAULT
AUTO GOVERNOR	If the computer can't keep up, Kiln eases off Ultra, then Eco, then voices, before the audio drops out. Off during offline bounces. The line under it shows its level.	On or off	On
SUB (SWITCH)	A dedicated sub oscillator.	On or off	Off
SUB: LEVEL	How loud the sub is.	0 to 100 %	60 %
SUB: SINE · TRIANGLE · SQUARE (WAVE)	Sine is the cleanest low end; Triangle and Square add buzz you hear on small speakers.	3 waves	Sine
SUB: -1 · -2 (OCTAVE)	One or two octaves below the note.	-1, -2	-1
NOISE (SWITCH)	A colored noise source beside the oscillators, through its own filter.	On or off	Off
NOISE: LEVEL	How loud the noise is.	0 to 100 %	40 %
NOISE: COLOR	Darker to the left, brighter to the right; white in the centre.	Dark 100 % to Bright 100 %	Flat (white)
NOISE: OFF · LP · HP · BP (NOISE FILTER)	The noise's own filter: off, low pass, high pass or band pass.	4 settings	Off
NOISE: FREQUENCY	Where the noise filter acts. Dim while the filter is Off.	20 Hz to 20 kHz	20.0 kHz
NOISE: KEYTRACK	On: the noise filter follows the note you play.	On or off	Off

14

The Motion page

Motion holds the modulation in three views, picked by **Envelopes**, **LFOs** and **Matrix** at the top right. The glass draws the shown envelope's or LFO's shape.

Envelopes



FIG. 14 The Envelopes view on Env 1, with its shape in the glass.

- 1

Env 1 to Env 4. Pick which envelope the controls show.
- 2

Attack, Decay, Sustain, Release. The envelope's stages.
- 3

Delay, Hold. A wait before the attack, and time at the top.
- 4

Curves. The shape of the attack, decay and release.
- 5

Velocity. How much harder playing raises it.
- 6

Loop. Repeats while the key is held.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
ENV 1 TO ENV 4	Four envelopes. Env 1 shapes each note's volume; Env 2 to Env 4 do nothing until a matrix route uses them.		
ATTACK	How long the rise takes.	0 ms to 20 s	5.0 ms
DECAY	How long it falls to the Sustain level.	1 ms to 30 s	600 ms
SUSTAIN	The level held while the key is down.	0 to 100 %	75 %

CONTROL	WHAT IT DOES	RANGE	DEFAULT
RELEASE	How long it fades after you let go.	1 ms to 30 s	120 ms
DELAY	A wait before the attack starts.	0 ms to 2 s	0 ms
HOLD	How long it stays at the top before the decay.	0 ms to 2 s	0 ms
ATTACK CURVE, DECAY CURVE, RELEASE CURVE	The shape of each stage: slow start to the left, fast start to the right, Even in the centre.	Slow 100 % to Fast 100 %	Even
VELOCITY	How much harder playing raises this envelope.	0 to 100 %	Env 1: 35 %; others 0 %
LOOP	On: the envelope repeats from the attack while the key is held.	On or off	Off

LFOs

An LFO moves nothing until a matrix route uses it as a source (see Matrix).



FIG. 15 The LFOs view on Glass Ladder: LFO 1 at 5.50 Hz, fading in over 500 ms.

- 1

LFO 1 to LFO 4. Pick which LFO the controls show.
- 2

Sync, One-shot, Per voice. Tempo sync, one cycle per note, one LFO per voice.
- 3

Rate. How fast it moves.
- 4

Shape. The wave the LFO draws.
- 5

Phase, Smooth. Where it starts, and how round it is.
- 6

Fade in. The time to full depth after each attack.

CONTROL	WHAT IT DOES	RANGE	DEFAULT
LFO 1 TO LFO 4	Four LFOs.		
SYNC	On: the LFO runs at a note value in time with your DAW, and Rate shows note values. Off: Rate is in Hz.	On or off	Off
ONE-SHOT	On: it runs once per note, then stops, like an extra envelope.	On or off	Off
PER VOICE	On: every note starts its own LFO. Off: one LFO moves every note together.	On or off	On
RATE	How fast it moves: free in Hz (the wheel steps a semitone), or a note value with Sync on.	0.01 to 200 Hz; 8/1 to 1/64	2.00 Hz; 1/8
SHAPE	Sine, Triangle, Saw (falling), Square, S&H (a random step each cycle) or Custom (it plays a sine; there is no shape editor). Click a word or turn the dial.	6 shapes	Sine
PHASE	Where in its cycle it starts at each note. With Per voice off, it offsets the shared LFO.	0 to 360°	0°
SMOOTH	Rounds the corners; tames S&H.	0 to 100 %	0 %
FADE IN	How long the LFO takes to reach full depth after each attack, so vibrato blooms on held notes. A legato slide does not start it again. At 0 ms it is off.	0 ms to 5 s	0 ms

Matrix



FIG. 16

The Matrix view on Turned Prism: eight routes, each a source, a target and a depth.

- | | |
|--|--|
| 1 Pages. Six pages of eight routes, 1–8 to 41–48. | 2 Source. What moves the target. |
| 3 Target. The control it moves. | 4 Depth. How far, and in which direction. |
| 5 Clear. Empties the route. | |

The matrix has 48 routes in six pages of eight, picked by **1–8** to **41–48**. Each route has a source, a target and a depth. Click **Choose a source** or **Choose a target** to pick from a menu (the targets are grouped by kind); turn the depth knob, from –100 to +100 %; **Clear** empties the route. Init has no routes; every factory sound uses some. A route you have only half made (a source without a target) stays put while you finish it.

Sources: Env 1 to Env 4, LFO 1 to LFO 4, Random, Chaos, Macro 1 to Macro 4, Velocity, Release Velocity, Note, Mod Wheel, Pitch Wheel, Aftertouch, MPE Pressure, MPE Slide, MPE Lift, and Gate Count (how many keys are held, full at eight).

Targets: each oscillator's Level, Pan, Pitch, Fine, Table Position, Warp Amount, Unison Detune, Unison Spread, FM Amount, Pulse Width, Shape and Sample Start; each filter's Cutoff, Resonance, Morph, Drive, Mix and Glass Material, Position, Damping and Shimmer; each envelope's Attack, Decay, Sustain and Release; each LFO's Rate; Sub Level, Noise Level, Noise Color, Drift, Drive Amount, Drive Mix and Pitch Env Amount (Knock); and the depth of any route (Mod 1 Depth to Mod 48 Depth). The effects are not targets.

The menus and the rows name each target in full, such as Osc 1 Table Position or Filter 1 Glass Material. Drive Amount and Drive Mix are the Drive view's large Drive knob and its Mix, and Pitch Env Amount is Knock. Warp Amount does nothing while that oscillator's Warp is Off.

To add movement: pick a source and a target, start the depth near zero, and raise it while you hold a note.

15

Settings in your DAW only

Almost every setting has a control on Kiln's face. These remain in your DAW's parameter list:

CONTROL	WHAT IT DOES	RANGE	DEFAULT
FILTER 1 FILTER FM SOURCE, FILTER 2 FILTER FM SOURCE	An oscillator that moves this filter's cutoff. Sub is also listed; it does nothing.	None, Osc 1, Osc 2, Osc 3, Sub	None
FILTER 1 FILTER FM, FILTER 2 FILTER FM	How far that oscillator moves the cutoff.	0.00 to 1.00	0.00
LFO 1 STEREO PHASE TO LFO 4 STEREO PHASE	Not active in 1.1: it does nothing.	0.00 to 0.50	0.00

16 Anneal and tuning

Anneal

Anneal starts a sound for you from a recording. Open it from **Options > Anneal from audio....**




FIG. 17

Anneal, waiting for a sound.

- | | |
|--|---|
| <p>1 Open Audio. Choose a file, or drop one on the panel.</p> <p>3 Close. Closes the panel and stops a search; so does a click outside the panel, or Esc.</p> <p>5 Status. What Anneal is doing.</p> | <p>2 Anneal. Starts the search.</p> <p>4 Drop area. Drop one audio file here.</p> |
|--|---|

To start a sound from a recording:

- 1 Click **Open Audio** and choose a short, isolated sound, or drop one on the panel: WAV, AIFF, FLAC, MP3 or OGG, mono or stereo. Anneal analyzes up to the first four seconds.
- 2 Click **Anneal** and wait. While it searches, **Cancel** appears; it stops the search and keeps the recording loaded.
- 3 Click **Apply** on each result (up to four) to hear it, then close the panel and shape the one you like with the normal controls.
- 4 Save it as a user sound.

The percentage on each result is how closely its features match, not a promise that it copies the recording. The analysis runs on your computer.

Tuning

In **Options**, under Tuning, choose **Load scale (.scl)...**, **Load keyboard map (.kbm)...** or **Reset tuning to 12-TET**. A scale alone maps from C4 at 261.63 Hz; a keyboard map sets the reference key and frequency. The scale and map are saved with your session.

While one is active, the header shows Scale: and its name (with + Map when a keyboard map is loaded); click it for the same items. When an MTS-ESP tuning master is running, the header reads MTS-ESP and the master's tuning takes over. A file Kiln cannot use shows Tuning refused with the reason.

17 Keyboard and mouse

Letters on your computer keyboard play notes, so Kiln's own shortcuts use digits, brackets and two letters.

ACTION	MAC	WINDOWS
Play notes (C upward)	a w s e d f t g y h u j k o l p ;	a w s e d f t g y h u j k o l p ;
Typing octave down or up	z or x	z or x
Open a page	1 to 8	1 to 8
Previous or next sound	[or]	[or]
Step through the Library and load	Up or Down	Up or Down
Load the selected Library row	Enter	Enter
Close the Library, Anneal or the shortcut sheet	Esc	Esc
Show the shortcut sheet	?	?
Fine drag on a knob	Shift + drag	Shift + drag
Reset a knob	Double-click, or Cmd + click	Double-click, or Ctrl + click
Step a knob on its grid	Mouse wheel (Shift for fine)	Mouse wheel (Shift for fine)
Type an exact value	Click the value	Click the value

In Pro Tools, fine drag is **Cmd** + drag (**ctrl** on Windows) and reset is **Option** + click (**Alt** on Windows). Typing into a box (a value, Search or the save name), or opening Anneal or the shortcut sheet, pauses the computer keys and releases any notes you were holding with them. The Library leaves them live, so you can play each sound as you pick it.

A typed value can use the units the readouts show: 2.75 kHz , -3 ct , 53 ms , 0.05 s , or 40% (40 alone works too on a control that reads in percent). On most percent controls a bare 1 or 0.5 is read as a fraction (100 % or 50 %), so add % to small values. Type off where a readout says Off. Kiln keeps the exact number you type, even when the readout rounds it.

18 Recipes

A sliding 808

SOUND	A bass from the 808 or Bass type
VOICE MODE	Legato
GLIDE	60 to 120 ms, with Exp
CLEAN LEGATO	On
KNOCK (DRIVE PAGE, KNOCK VIEW)	+7 to +12 st, Decay 30 to 60 ms
MACRO PUNCH	30 to 60 % for more knock

Play overlapping notes to slide; leave a gap to re-attack.

Chords that glide

SOUND	A pad or lead
VOICE MODE	Poly
CHORD GLIDE	On (Glide starts at 180 ms)
GLIDE	150 to 300 ms

Play a chord progression, letting go of each chord just before you play the next one. Every voice slides to its nearest new note.

Grit on a sub without losing the sub

SOUND	A sustained sub bass from the Bass type
DRIVE	On, Type Fuzz or Even
DRIVE (THE LARGE KNOB)	12 to 24 dB
LOW KEEP	80 to 120 Hz
BIAS	30 to 60 %
BASS MONO (CLIPPER VIEW)	100 Hz

The drive adds harmonics above Low Keep while the sub stays clean and centred.

A lead with vibrato that blooms

SOUND	One of the new leads, such as Glass Ladder
MACRO VIBRATO	40 to 70 %
LFO 1 FADE IN (MOTION PAGE, LFOS VIEW)	300 to 800 ms

Short notes stay straight; held notes open into vibrato.

A filter wobble

SOUND	A bass or a lead
FILTER 1	On, with the oscillator's Route (Source page, Pitch view) on Filter 1 or Both
FILTER 1 CUTOFF	300 to 800 Hz
MATRIX ROUTE (MOTION PAGE)	Source LFO 1, target Filter 1 Cutoff
DEPTH	Start near 0 % and raise it while you hold a note
LFO 1 RATE (LFOS VIEW)	2 to 6 Hz

Hold a note: the filter opens and closes with LFO 1.

A glass pluck

SOUND	A Keys or Pluck sound with the Glass character word
FILTER 1 MODEL	Glass
MATERIAL	10 % for glass, 50 % for metal, 90 % for wood
DAMPING	Lower for a longer ring

19

Quality, CPU and old sessions

Quality (Eco, Standard, Ultra) on the Output page trades CPU against quality.

Offline bounces always run Ultra, so you can work on Eco and still bounce clean, if your DAW tells Kiln it is bouncing offline. A real-time export may not, so set Ultra yourself before a real-time export.

Auto governor keeps playback running under heavy load by easing off Ultra, then Eco, then voices.

Unison is the biggest CPU cost: each extra unison voice (Source page, **Unison** view) is another oscillator per note.

Old sessions keep the old engine. A project or user sound saved with Kiln 0.3 or earlier opens with the engine it was made with, including the old filter drive, soft clip and voice stealing, so it sounds exactly as you left it. Every control new in 1.0 starts off in those sessions. A project saved with Kiln 1.0 likewise keeps its Chord Glide, its matrix and warp, and the six wavetables as 1.0 played them.

20

Specifications

Voices: up to 64 in Poly (16 by default).

Latency: none.

Sounds: 683 factory sounds and 80 wavetables.

Samples: WAV, AIFF or FLAC; the first 2,097,152 samples of a file.

Window: 1280 × 860 when it opens; resizable from 1120 × 752 to 1920 × 1290, keeping its shape.

Formats: VST3 and AAX on macOS and Windows; AU on macOS.

Systems: macOS 10.15 or later on Intel, macOS 11 or later on Apple Silicon; Windows 10 or later, 64-bit.

Credits

Interface type: Archivo, copyright 2020 The Archivo Project Authors, used under the SIL Open Font License, Version 1.1.

Tuning: the MTS-ESP client library, copyright 2021 ODDSound Ltd., used under its license.

21 Installation and updates

Install

- 1 Save your work and quit your DAW.
- 2 Install **Kiln Synthesizer** from the Muse Hub app. Muse Hub downloads it and puts the plugins in place.
- 3 Open your DAW. If Kiln Synthesizer is not listed, run your DAW's plugin rescan.

Use AU in Logic Pro, AAX in Pro Tools and VST3 in other DAWs. On a Mac the plugins go in the standard folders:

AU: `/Library/Audio/Plug-Ins/Components`

VST3: `/Library/Audio/Plug-Ins/VST3`

AAX: `/Library/Application Support/Avid/Audio/Plug-Ins`

On Windows, Muse Hub installs the VST3 and AAX versions.

Nothing to enter

This edition opens and runs as soon as it is installed. Your Muse Hub purchase is your license: there is no key, code or account to enter, and nothing to unlock. The license word in the header reads Muse Hub. It is a label, not a button, so clicking it does nothing.

Muse Hub handles the purchase, any trial and any payment question under its own terms. Vitric sets no limit of its own on the number of computers: install Kiln on the computers you personally use, within Muse Hub's terms.

Updates

Updates to this edition are free and come through Muse Hub. When a new version is out, save your work, quit your DAW and update Kiln in the Muse Hub app. Your sessions reopen exactly as saved after every update.

Kiln never checks for updates itself in this edition and shows no update notice, whatever the **Check for updates** option is set to.

Sessions and presets are the same as in the vitricaudio.com edition of Kiln Synthesizer, so your projects open in either edition.

22

Troubleshooting

No sound

Kiln is an instrument: check that it is on an instrument (MIDI) track, the track is armed or monitoring, and notes reach it (the keys light when they do).

If one oscillator is silent, its **Ring** may be taking its signal from an oscillator that is off or at Level 0 (the one in **FM from**, Source page, **Pitch** view). Turn that oscillator on, or Ring off.

On the Source page, check that an oscillator is on with its **Level** up, and that **Out** is not turned down.

On the Filter page, check that **Cutoff** on an active filter is not turned all the way down.

The pattern keeps playing after I let go

Latch is on in the arpeggiator. Turn it off.

I can't find a control

Most pages show one part at a time. Click the words at a page's top right: **Arp** and **Voice** on the Voice page; **Sound**, **Unison** and **Pitch** on the Source page (for each of Osc 1 to Osc 3); **Drive**, **Knock** and **Clipper** on the Drive page; **Output**, **Sub** and **Noise** on the Output page; **Envelopes**, **LFOs** and **Matrix** on the Motion page. On the Filter page, **Filter 1** and **Filter 2** pick the filter; on the Motion page, the words above the controls pick the envelope, the LFO or the page of routes. The Effects page shows one effect at a time: click its name. The Drive page starts on the Drive view each time Kiln's window opens. Filter FM is the one working setting left only in your DAW (see Settings in your DAW only).

A control does nothing

Table, Position and Warp work on Wavetable oscillators; Shape, Pulse width and Sync (Sound view) on Analog; Start, Loop, Reverse and Crossfade on Sample. Warp amount does nothing while Warp is Off.

FM amount needs **FM from** set to a higher-numbered oscillator that is on (Source page, **Pitch** view), and Ring needs FM from set to a higher-numbered oscillator. On a Sample oscillator, FM amount and the Sync switch (Pitch view) do nothing.

On the Filter page, Drive works on the Ladder and Slope on the SVF; Balance works in Split.

On the compressor, Ratio works in Clean, and Upward and Downward in OTT.

The noise filter's Frequency does nothing while its filter is Off.

Bias does nothing on Soft, Hard and Fold drive; the note under it says so.

Decay, Curve and On slides do nothing while Knock is Off, unless a matrix route moves Pitch Env Amount (the Punch macro on the new basses does).

The Clipper's Drive and Knee do nothing while the Clipper is off.

An LFO, and Env 2 to Env 4, move nothing until a matrix route uses them.

Chord Glide does nothing in Mono or Legato (it reads Needs Poly) or while Glide is Off.

A macro that reads Not assigned is not used by this sound; route it on the Motion page.

Notes slide when I don't want them to, or don't slide

Notes slide in Mono and Legato when they overlap, and in Poly with **Chord Glide** on. With **Legato only** off (Voice page, **Voice** view), every note slides from the last one, in any voice mode. To stop it, set **Glide** to Off, turn Chord Glide off, turn Legato only back on, or (in Mono and Legato) leave a gap between notes. If nothing slides, check that Glide is above Off and that the notes overlap.

The computer keys or shortcuts do nothing

Click an empty part of Kiln's window once so it has the keyboard. Typing into a box (a value, Search or the save name), or an open Anneal panel or shortcut sheet, pauses the computer keys; after typing in the Library, click the list to play again. Some DAWs keep certain keys for themselves; use your MIDI keyboard or the on-screen keys for those.

It crackles or my computer runs short

Lower the unison **Voices** on the oscillators (Source page, **Unison** view), choose **Eco** under Quality on the Output page, keep **Auto governor** on, or raise your DAW's buffer size. Offline bounces still run Ultra.

The end of my bounce cuts off the reverb or delay

Leave a few bars after the last note inside the export range, or turn on your DAW's option to include effect tails.

I can't find an old bass

In the Library, choose **All sounds**, then the **Legacy** shelf, last under Packs: the earlier factory sounds are there, and every sound keeps its name. Pick a type with it, such as Bass, or search: in All sounds "legacy bass" finds the older basses.

Kiln does not appear in my DAW

Rescan plugins and restart the DAW. In Logic Pro, use Logic Pro > Settings > Plug-in Manager and **Reset & Rescan Selection**. Look for Kiln among instruments, not effects.

23

Support

Muse Hub provides first-line support for this edition and passes anything it cannot solve, such as a plugin fault, on to Vitric. You can also write to support@vitricaudio.com with your Kiln version, operating system, DAW and version, plugin format and the exact error if there is one.

Kiln Synthesizer user manual, Muse Hub edition, version 1.1.0, updated October 21, 2026.

© 2026 Vitric Audio. vitricaudio.com