



DEEPER

INTRODUCTION:


Deeper fills the room with low sonic frequencies and enhances the frequency content that already exists with its internal sub-enhancing algorithms.

Deeper comes with controls to dictate how the plug-in behaves in the low end of the frequency spectrum. For example, the thump generates a deep sub-oscillation based off RMS values.

There is really no wrong way to use Deeper, but we suggest using it for kicks and on subs.



OVERVIEW



(0) The Gooley Icon: When hovering the mouse over the icon, a tooltip will appear, which will provide the version number of the product.

(0b) When clicking on the Gooley icon the plugin will be bypassed. To indicate it is bypassed, the icon will change color, and a tooltip will appear.

(1) Preset Scroll Buttons: click to scroll through the list of presets.

(2) Preset Menu: click to see the full list of saved presets. *Note: Press Ctrl+z to undo and Ctrl+y to redo.*

(3) Deep Button: Overlays a subtle saturation and shelf at sixty hertz.

(4) Level Slider: Controls the output of Deeper, and ranges between -12db and +6db. *You can use the level slider to overdrive and saturate the Deeper driver.*

(5) Blend Slider: The blend slider intermits a transmission between the input and the output.

(6) Tail Slider: The tail slider elongates the passage of time from the generated sub-oscillator. For a deep, long, resonant bass, turn up the tail.

(7) Freq Slider: The Freq slider controls the pitch or frequency of the generated oscillator. For added control, there's a dropdown menu that can be used to snap the frequency to a specific note.

(8) Thump Slider: The thump slider provides girth to the signal, as it generates and amplifies a low-frequency oscillation..

(10) X-Over: Determines the frequency crossover. For deeper-darker and more focused subs, the X-Over will be engaged to the left with a cutoff of seventy hertz. *Note, the roll-off of the bass shelf occurs at twelve decibels per octave.*

(9) Deeper Control: The deeper control pushes a subtle saturation into a shelf filter. As the control is engaged, both the saturation and the shelf increase.

Warning: when boosted levels are too loud, a harshness will appear in the bass. Try pulling back the dial until a thick, warm bass is heard, but without distortion.

Note, Deeper is not an additive plug-in, and it is also not to be used to distort low frequencies, as only a portion of the signal will be amplified and saturated.

(11) Preset Save Icon: Click to save a preset. Presets will be stored in a local user file folder.

BACK TO DEEPER

Instruction Manual – V1.0.0 – last updated 1/1/2026



